


Simplicity®

3708


1 / 4

Thank you for purchasing this Simplicity pattern.
We have made every effort to provide you with a high quality product.
Gracias por haber comprado este patrón de Simplicity.
Hemos hecho todos los esfuerzos para ofrecerle un producto de alta calidad.



Sign-up for our **free** newsletter
today at **simplicity.com**

17 pieces given



- 1-FRONT

2-FRONT INTERFACING

3-UPPER POCKET

4-LOWER POCKET

5-SIDE PANEL

6-BACK

7-UPPER COLLAR

8-UNDER COLLAR

9-COLLAR STAND
- 10-FRONT FACING

11-BACK LINING

12-ARMHOLE FACING

13-UPPER SLEEVE

14-UNDER SLEEVE


15-PATCH -A

16-YOKE FRONT -B

17-YOKE BACK -B

Cutting

Layouts



POSITION OF PATTERN PIECES MAY VARY SLIGHTLY ACCORDING
TO YOUR PATTERN SIZE

BOYS'


A,B JACKET

USE PIECES 1 3 4 5 6 7 8 9 10 12 13 14


B- CUT ONE OF PIECE 3

1A 44" 45" (115CM) WITH NAP
ALL SIZES

PIECE 15 IS OPTIONAL AND CUT OF FABRIC REMNANT



1B 58" 60" (150CM)
WITH NAP
ALL SIZES



LINING

USE PIECE 11

1C 44" 45" (115CM)
WITHOUT NAP
ALL SIZES




INTERFACING

USE PIECES 2 3 4 7 8 9 10 15

PIECE 15 IS OPTIONAL
B- CUT ONE OF PIECE 3


1D 22" TO 25" (55CM TO 64CM) FUSIBLE
ALL SIZES



B YOKE

USE PIECES 16 17

2 44" 45" OR 58" 60" (115CM OR 150CM)
WITH NAP
ALL SIZES



U.S. & Canada Toll-Free
1-888-588-2700

Web Site
<http://www.simplicity.com>

E-mail
info@simplicity.com

General Directions

The Pattern

↔

GRAIN LINE Place on straight grain of fabric parallel to selvage

⇄

PLACE SOLID LINE on fold of fabric.

CENTER FRONT OR BACK of garment.

▽▽

NOTCHES

• •

DOTS

—

CUTTING LINE

==

LENGTHEN OR SHORTEN LINES

ADJUST IF NEEDED

Make adjustments before placing pattern on fabric.


TO LENGTHEN: Cut pattern between lengthen or shorten lines. Spread pattern evenly, the amount needed and tape to paper.

TO SHORTEN: At lengthen or shorten lines, make an even pleat taking up amount needed. Tape in place.

When lengthen or shorten lines are not given, make adjustments at lower edge of pattern.

Sewing

- SEW garment following **Sewing Directions**.
- PIN or machine-baste seams matching notches.
- STITCH 5/8" (1.5 cm) seams unless otherwise stated.
- PRESS seams open unless otherwise indicated clipping when necessary so seams will lie flat.
- TRIM seams to reduce bulk, as shown below.



Cutting/Marking

BEFORE CUTTING:

PRESS pattern pieces with a warm dry iron. PRE-SHRINK fabric by pre-washing washables or steam-pressing non-washables.

CIRCLE your cutting layout.

PIN pattern to fabric as shown in Cutting Layouts.

FOR DOUBLE THICKNESS: Fold fabric with RIGHT sides together.

FOR SINGLE THICKNESS: Place fabric RIGHT side up.

FOR PILE, SHADED OR ONE WAY DESIGN FABRICS: Use "with nap" layouts

AFTER CUTTING:

Transfer markings to WRONG side of fabric before removing pattern. Use pin and chalk method or dressmaker's tracing paper and wheel.

To Quick Mark:

- Snip edge of fabric to mark notches, ends of fold lines and center lines.
- Pin mark dots.

SPECIAL CUTTING NOTES

★ If layout shows a piece extending past fold, cut out all pieces except piece that extends.

Open out fabric to single thickness. Cut extending piece on RIGHT side of fabric in position shown.

✱ Mark small arrows along both selvages indicating direction of nap or design. Fold fabric crosswise with RIGHT sides together, and cut along fold (a).

Turn one fabric layer around so arrows on both layers go in the same direction. Place RIGHT sides together (b).

MEN'S

A,B JACKET

USE PIECES 1 3 4 5 6 7 8 9 10 12 13 14

B- CUT ONE OF PIECE 3

3A 44" 45" (115CM) WITH NAP
ALL SIZES

PIECE 15 IS OPTIONAL AND CUT OF FABRIC REMNANT

3B 58" 60" (150CM)
WITH NAP
SIZES S M

3C 58" 60" (150CM) WITH NAP
SIZES L XL

CUTTING LAYOUTS CONTINUE ON PAGE 2

Español

NIÑOS

A,B CHAQUETA USE PIEZAS 1 3 4 5 6 7 8 9 10 12 13 14
B- CORTAR UNO DE LA PIEZA 3

1A 44" 45" (115CM) CON PELUSA/ TODAS LAS TALLAS
PIEZA 15 ES OPCIONAL Y SE CORTA DE UN RETAZO DE TELA

1B 58" 60" (150CM) CON PELUSA/ TODAS LAS TALLAS

FORRO USE PIEZA 11

1C 44" 45" (115CM) SIN PELUSA / TODAS LAS TALLAS

ENTRETELA USE PIEZAS 2 4 7 8 9 10 15
PIEZA 15 ES OPCIONAL / B- CORTAR UNO DE LA PIEZA 3

1D 22" A 25" (55CM A 64CM) ADHESIVA / TODAS LAS TALLAS

B CANESÚ USE PIEZAS 16 17

2 44" 45" O 58" 60" (115CM O 150CM) CON PELUSA
TODAS LAS TALLAS

HOMBRES

A,B CHAQUETA

USE PIEZAS 1 3 4 5 6 7 8 9 10 12 13 14

B- CORTAR UNO DE LA PIEZA 3

3A 44" 45" (115CM) CON PELUSA/ TODAS LAS TALLAS
PIEZA 15 ES OPCIONAL Y SE CORTA DE UN RETAZO DE TELA

3B 58" 60" (150CM) CON PELUSA / TALLAS P M

3C 58" 60" (150CM) CON PELUSA / TALLAS G XG

SELVAGE (S) / SEL. =ORILLA
FOLD =DOBLEZ
CROSSWISE FOLD =DOBLEZ TRANSVERSAL
SINGLE THICKNESS = ESPESOR SIMPLE

VER LA PAGINA 2

© Copyright 2007—Simplicity Pattern Co., Inc. / Printed in U.S.A. / Simplicity is a registered trademark of Simplicity Pattern Co., Inc.


3708

2 / 4

LINING

USE PIECE 11


3D 44" 45" (115CM)
WITHOUT NAP
ALL SIZES



INTERFACING

USE PIECES 2 3 4 7 8 9 10 15
PIECE 15 IS OPTIONAL
B- CUT ONE OF PIECE 3


3E 22" TO 25"
(55CM TO 64CM)
FUSIBLE
ALL SIZES



B YOKE

USE PIECES 16 17

4 44" 45" OR 58" 60" (115CM OR 150CM)
WITH NAP
ALL SIZES



Español

FORRO USE PIEZA 11

3D 44" 45" (115CM) SIN PELUSA/ TODAS LAS TALLAS

ENTRETELA USE PIEZAS 2 3 4 7 8 9 10 15

PIEZA 15 ES OPCIONAL / B- CORTAR UNO DE LA PIEZA 3

3E 22" A 25" (55CM A 64CM) ADHESIVA / TODAS LAS TALLAS

B CANESÚ USE PIEZAS 16 17

4 44" 45" O 58" 60" (115CM O 150CM) CON PELUSA
TODAS LAS TALLAS

Sewing Directions

FABRIC KEY	RIGHT SIDE	WRONG SIDE	INTERFACING	LINING

Read **General Directions** on page 1 before you begin.

GENERAL DIRECTIONS FOR APPLYING DOUBLE FOLD BIAS TAPE

The tape comes prefolded, with one side slightly wider than the other. The wider side is to be used on the **WRONG** side of the garment so that when the tape is stitched in place from the **RIGHT** side, both edges are sure to be caught in the stitching.

Ends:

Turn tape ends under to finish or enclose in the seam when possible.







When tape completely encloses an edge, arrange to have ends meet at a seam; then turn both ends under where they meet and tack together invisibly after stitching on tape.

This will be referred to as **ENCASE** in guide sheet.

JACKET A OR B

NOTE: For View A, elbow patches are optional.



- Stay-stitch front and back neck edges 1/2" (1.3cm) from cut edge in direction of arrows. This stitching stays in permanently and helps prevent stretching on curved edges. Stay-stitching will not be shown in the following illustrations.
- Pin fusible interfacing to **WRONG** side of each front. Cut diagonally across corners that will be enclosed with seams. Fuse, following manufacturer's directions.
- To make dart in front with **RIGHT** sides together, fold the fabric through the center of the dart, bringing broken lines and small dots together. On **INSIDE**, place pins at **RIGHT** angles to the broken lines. Stitch the dart from the middle to one point. Then, overlapping several stitches, work from the middle to the other point. If necessary, carefully clip the dart at its widest point so that it will lie flat.
TIP- To prevent a "bubble" at each point, make the last few stitches right on the fold and leave the thread ends long enough to tie a knot. **DO NOT** back-stitch at the points. Press the dart flat along the stitching to "blend" the stitches, then press dart toward center.



- To finish long edge of vent extension on side panel, press under 5/8" (1.5cm) on raw edge of extension. To form narrow hem, tuck under raw edge to meet crease. Press. Stitch hem in place.
With **RIGHT** sides together, pin front to side panel at side front seam. Stitch. Press seam open and **ENCASE** edges.
- Pin fusible interfacing to **WRONG** side of each lower pocket. Fuse, following manufacturer's directions. Press under 1/4" (6mm) on upper edge of pocket. Turn upper edge to **OUTSIDE** along fold line, forming facing. Stitch along seam line on raw edges; trim to 1/4" (6mm).
- Turn facing to **INSIDE**, turning under raw edges along stitching; press. Stitch facing close to inner edge.
- On **OUTSIDE**, pin pocket to front and side panel, placing upper corners at large dots. For View A, stitch close to side and lower edges. For View B, stitch close to side and lower edges and 1/4" (6mm) away.
Prepare upper pocket in same manner as lower pocket.
- FOR VIEW A** - On **OUTSIDE**, pin upper pocket to **LEFT** front, placing upper corners at large dots. Stitch close to side and lower edges.
- FOR VIEW A OR B** - Stitch center back seam of back. Press seam open. **ENCASE** seam allowances. To ease back shoulder edges between notches, stitch along seam line and 1/4" (6mm) **INSIDE** seam line, using a long machine-stitch. Press under 5/8" (1.5cm) on raw edge of back vent extensions. Baste close to fold.

3708



3 / 4



- 10.** With RIGHT sides together, pin back to side panel at side back seam, matching notches and large dots. To stitch side back seam and form vents, stitch along seam line from armhole edge to large dot. Back-stitch at dot to reinforce seam. Machine-baste along solid line from large dot to lower edge.


TIP - The vent is basted closed to achieve a crisp fold after the vent is pressed in place.

- 11.** Reinforce inner corner and stitch upper end of vent extensions together as follows:
Starting 1" (2.5cm) above large dot, stitch along seam line to large dot; pivot at large dot and stitch across upper end of vent extensions. Press seams and vent extensions toward back. **ENCASE** seam allowances together. Baste upper end of vent extension in place along stitching.




- 12.** On OUTSIDE, stitch back along basting on vent, as shown. Remove bastings from vents.

- 13.** With RIGHT sides together, pin front to back at shoulder seams. Pull up ease stitches to fit. Baste. Stitch shoulder seams.




YOKE B


- 14.** Stay-stitch yoke front and yoke back neck edges 1/2" (1.3cm) from cut edge in direction of arrows. This stitching stays in permanently and helps prevent stretching on curved edges. Stay-stitching will not be shown in the following illustrations.




- 15.** To ease yoke back shoulder edges between notches, stitch along seam line and 1/4" (6mm) INSIDE seam line, using a long machine-stitch.



- 16.** With RIGHT sides together, pin yoke front to yoke back at shoulder seams. Pull up ease stitches to fit. Baste. Stitch seams.
Press under 3/8" (1cm) on front and lower edges of yoke front and on lower edge of yoke back, folding out fullness at points.




- 17.** Pin WRONG side of yoke to RIGHT side of garment at neck edge, matching centers back, small dots, shoulder seams and having raw edges even. Pin pressed edges in place. Stitch close to pressed edges and 1/4" (6mm) away. Baste raw edges together.




CONTINUE AS FOLLOWS FOR VIEW A OR B


- 18.** Pin fusible interfacing to WRONG side of under collar and each collar stand. Cut diagonally across corners that will be enclosed with seams. Fuse, following manufacturer's directions.




- 19.** With RIGHT sides together, pin under collar to straight edge of collar stand, matching centers and small dots. Stitch seam. Trim seam allowances to 3/8" (1cm). Press seam open.




- 20.** On OUTSIDE, stitch close to each side of seam.




- 21.** Clip garment neck edge to stay-stitching along curves.
With RIGHT sides together, pin collar stand and under collar to neck edge of garment, matching centers back, small and large dots, placing inner small dot at shoulder seam. Stitch between large dots. Clip front to large dot. Trim seam; clip curves. Press seam open between large dots.




- 22.** Pin fusible interfacing to WRONG side of each front facing and upper collar. Cut diagonally across corners that will be enclosed with seams. Fuse, following manufacturer's directions.
ENCASE unnotched edge of front facing.




- 23.** On OUTSIDE, pin upper pocket to LEFT front facing, placing upper corners at large dots. Stitch close to side and lower edges.



- 24.** Press under hem allowance on lower edge of each back lining. To form narrow hem, tuck under raw edge to meet crease. Press. Stitch hem in place.












- 25.** On OUTSIDE, lap LEFT back lining over RIGHT back lining, matching centers and having neck and shoulder edges even. Baste raw edges together. To ease back shoulder edges between notches, stitch along seam line and 1/4" (6mm) INSIDE seam line, using a long machine-stitch.



- 26.** Stay-stitch neck edges of front facing and back lining 1/2" (1.3cm) from cut edge in direction of arrows. Stay-stitching will not be shown in the following illustrations.

3708

4 / 4



27. With RIGHT sides together, pin front facings to back lining at shoulder seams. Pull up ease stitches to fit. Baste. Stitch shoulder seams.

28. Prepare upper collar and stitch to remaining collar stand in same manner as under collar, see steps 18, 19 and 20. Clip neck of facing to stay-stitching. With RIGHT sides together, pin collar stand and upper collar to neck edge of front facing and back lining, matching centers back, small and large dots, placing inner small dot at shoulder seam. Stitch between large dots. Clip front facing to large dot. Trim seam; clip curves. Press seam open between large dots.

29. With RIGHT sides together, pin facing and upper collar to jacket and under collar, matching centers back, small and large dots. Baste, easing facing and upper collar to fit. Stitch front and collar edges, breaking stitching at large dots. Trim seam and corners; clip curves.

30. Turn facing and upper collar to INSIDE; press, pressing up hem. Tack collar stand seams together loosely. Baste front facing and back lining to armhole, matching shoulder seams.










31. Turn back vent extensions to OUTSIDE on solid lines. Stitch exactly 1-1/2" (3.8cm) above lower edge for Men's sizes OR 1-1/4" (3.2cm) for Boys sizes. Trim extensions close to stitching. Trim garment to within 5/8" (1.5cm) of inner edge of extension.

32. Turn vents to INSIDE. Press. Press under 1/4" (6mm) on raw edge of hem. Stitch back hem in place continuing to stitch across vents, then stitch side panel hems from vent to side back seam. Stitch inner edge of back vents in place. Slip-stitch front hem in place, slip-stitching inner edge of facing to hem.

33. On OUTSIDE, top-stitch 1/4" (6mm) from finished front and collar edges, squaring stitching at corners.

34. ENCASE raw edge of upper sleeve extension. Pin upper sleeve to under sleeve at back seam, matching large dots and easing back edge of upper sleeve to fit between notches. Stitch seam from upper edge to large dot. Back-stitch at large dot to reinforce seam.

35. ENCASE lower edges of sleeve sections. With RIGHT sides together, fold lower corner of upper sleeve, matching seam lines and having encased edges even. Stitch corner in a 3/8" (1cm) seam.



36. Turn corner to INSIDE. Press, pressing extension along solid line. Baste inner edge of extension in place.

37. On OUTSIDE, make buttonholes at markings. DO NOT cut buttonholes open.

38. Turn hem allowance to INSIDE on lower edge of under sleeve. Pin raw edges of hem and extension together. **ENCASE** raw edges together.

39. FOR VIEW A - Apply fusible interfacing to WRONG side of each patch, following manufacturer's directions. Press under 3/8" (1cm) on outer edge of patch, easing fullness. On OUTSIDE, pin patch to sleeve, matching large dots. Baste. Stitch close to pressed edge and 1/4" (6mm) away.

40. FOR VIEW A OR B - With RIGHT sides together; pin front seam of sleeve, matching notches and having encased edges even. Stitch, stretching upper sleeve to fit. Press seam open and **ENCASE** seams. Lap upper sleeve over under sleeve and on INSIDE, slipstitch encased edges of vent extensions together

41. To ease top of sleeve between notches, stitch along seam line and 1/4" (6mm) INSIDE seam line, using a long machine-stitch.

42. Turn sleeve RIGHT side out. Hold garment WRONG side out with armhole toward you. With RIGHT sides together, pin sleeve to armhole edge with center small dot at shoulder seam, matching front seam on sleeve to side front seam and remaining small dots. Pull up ease stitches to fit. To distribute fullness evenly, slide fabric along bobbin threads until there are no puckers or tucks on the seam line. Baste.

43. ENCASE unnotched edge of armhole facing. With WRONG sides together, pin facing to underarm, matching small dots and notches. Baste. Stitch entire armhole. Stitch again 1/8" (3mm) from first stitching. Trim seam below notches close to stitching. Press only the seam allowance, shrinking out fullness. **ENCASE** armhole seam through all thicknesses.

44. Try on garment. Insert shoulder pad and adjust to fit until it looks right and feels comfortable. Pin in place. Remove garment. On INSIDE, catch-stitch pad to shoulder seam.

NOTE: Men's Sizes uses 3/4" (2cm) buttons for front and 5/8" (1.5cm) buttons for sleeves.

If pattern has been altered, respace buttonhole markings. Make buttonholes in LEFT front.

Lap LEFT front over RIGHT, matching centers. Sew buttons under buttonholes.

Sew buttons over buttonholes on lower edge of sleeve through all thicknesses.