



Simplicity[®]/MD 1282 1 / 4

Thank you for purchasing this Simplicity pattern.
We have made every effort to provide you with a high quality product.
Gracias por haber comprado este patrón de Simplicity.
Hemos hecho todos los esfuerzos para ofrecerle un producto de alta calidad.



Sign-up for our **free** newsletter today at **simplicity.com**

10 pieces given



- 1-FRONT -A,B,C,D,E,F
- 2-SIDE FRONT -A,B,C,D,E,F
- 3-BACK -A,B,C,D,E,F
- 4-SIDE BACK -A,B,C,D,E,F
- 5-UPPER FRONT WAISTBAND -A,B,C,D,E,F
- 6-LOWER FRONT WAISTBAND -A,B,C,D,E,F
- 7-UPPER BACK WAISTBAND -A,B,C,D,E,F
- 8-LOWER BACK WAISTBAND -A,B,C,D,E,F
- 9-FRONT FACING -A,B,C,D,E,F
- 10-BACK FACING -A,B,C,D,E,F

General Directions

The Pattern

SYMBOLS

↔ GRAIN LINE Place on straight grain of fabric parallel to selvage

⇓ PLACE SOLID LINE on fold of fabric.

--- CENTER FRONT OR BACK of garment.

▽▽ NOTCHES

• DOTS

— CUTTING LINE

== LENGTHEN OR SHORTEN LINES

SEAM ALLOWANCE: 5/8" (1.5cm) unless otherwise stated is included but not printed on MULTI-SIZE PATTERNS. Mark your size with colored felt tip pen. See chart on tissue for how to use MULTI-SIZE PATTERNS.

ADJUST IF NEEDED

Make adjustments before placing pattern on fabric.


TO LENGTHEN: Cut pattern between lengthen or shorten lines. Spread pattern evenly, the amount needed and tape to paper.

TO SHORTEN: At lengthen or shorten lines, make an even pleat taking up amount needed. Tape in place.

When lengthen or shorten lines are not given, make adjustments at lower edge of pattern.

Sewing

- SEW garment following **Sewing Directions**.
- PIN or machine-baste seams matching notches.
- STITCH 5/8" (1.5 cm) seams unless otherwise stated.
- PRESS seams open unless otherwise indicated clipping when necessary so seams will lie flat.
- TRIM seams to reduce bulk, as shown below.



Cutting/Marking

BEFORE CUTTING:

PRESS pattern pieces with a warm dry iron. PRE-SHRINK fabric by pre-washing washables or steam-pressing non-washables.

CIRCLE your cutting layout.

PIN pattern to fabric as shown in Cutting Layouts.


- FOR DOUBLE THICKNESS: Fold fabric with RIGHT sides together.
- FOR SINGLE THICKNESS: Place fabric RIGHT side up.
- FOR PILE, SHADED OR ONE WAY DESIGN FABRICS: Use "with nap" layouts

AFTER CUTTING:

Transfer markings to WRONG side of fabric before removing pattern. Use pin and chalk method or dressmaker's tracing paper and wheel.

To Quick Mark:

- Snip edge of fabric to mark notches, ends of fold lines and center lines.
- Pin mark dots.



SPECIAL CUTTING NOTES

★ If layout shows a piece extending past fold, cut out all pieces except piece that extends.

Open out fabric to single thickness. Cut extending piece on RIGHT side of fabric in position shown.

✱ Mark small arrows along both selvages indicating direction of nap or design. Fold fabric crosswise with RIGHT sides together, and cut along fold (a).

Turn one fabric layer around so arrows on both layers go in the same direction. Place RIGHT sides together (b).

Cutting Layouts

pattern printed side down

pattern printed side up

★ See SPECIAL CUTTING NOTES


✱

POSITION OF PATTERN PIECES MAY VARY SLIGHTLY ACCORDING TO YOUR PATTERN SIZE

C,D,E NOTE: LEATHER-LIKE FABRICS, ALTER TISSUE PATTERN BEFORE CUTTING. PLACE PINS WITHIN SEAM ALLOWANCE OR USE MASKING TAPE. DO NOT USE A TRACING WHEEL TO TRANSFER MARKING.

A,B,C,D,E,F INTERFACING

- USE PIECES 5 6 7 8 9 10
- 1** 20" TO 25" (51CM TO 64CM) FUSIBLE ALL SIZES





NOTE: DASHED LINE SHOWN ON PATTERN PIECES IN CUTTING LAYOUTS INDICATES CUTTING LINE FOR SHORTER LENGTH

A,B,C,D SKIRT

USE PIECES 1 2 3 4 5 6 7 8 9 10

- 2A** 44" 45" (115CM) WITH NAP ALL SIZES



E SKIRT

USE PIECES 1 2 3 4 5 6 7 8 9 10


- 3A** 44" 45" (115CM) WITH NAP ALL SIZES

- 3B** 58" 60" (150CM) WITH NAP ALL SIZES

F SKIRT

USE PIECES 1 2 3 4 5 6 7 8 9 10

- 4A** 44" 45" (115CM) WITH NAP ALL SIZES



- 4B** 58" 60" (150CM) WITH NAP SIZES 6 8 10 12 14 16


- 4C** 58" 60" (150CM) WITH NAP SIZES 18 20 22

CONTRAST FRONT OVERLAY AND LOWER WAISTBAND OVERLAY

USE PIECES 1 6 8

- 4D** 44" 45" (115CM) WITH NAP ALL SIZES

- 4E** 58" 60" (150CM) WITH NAP ALL SIZES



Español

C,D,E NOTA: PARA LOS CUEROS SINTÉTICOS, AJUSTE EL PATRÓN ANTES DE CORTAR. COLOQUE LOS ALFILERES EN EL MARGEN DE COSTURA O USE CINTA ADHESIVA NO USE LA CARRETILLA PARA TRANSFERIR LAS MARCAS

A,B,C,D,E,F ENTRETELA

USE LAS PIEZAS 5 6 7 8 9 10

- 1** 20" A 25" (51CM A 64CM) ADHESIVA / TODAS LAS TALLAS

NOTA: LA LÍNEA INTERRUMPIDA EN LAS PIEZAS DE LOS DIAGRAMAS DE CORTE INDICA LA LÍNEA DE CORTE PARA LOS MODELOS CORTOS

A,B,C,D FALDA

USE LAS PIEZAS 1 2 3 4 5 6 7 8 9 10

- 2A** 44" 45" (115CM) CON PELUSA / TODAS LAS TALLAS
- 2B** 58" 60" (150CM) CON PELUSA / TODAS LAS TALLAS

E FALDA USE LAS PIEZAS 1 2 3 4 5 6 7 8 9 10

- 3A** 44" 45" (115CM) CON PELUSA / TODAS LAS TALLAS
- 3B** 58" 60" (150CM) CON PELUSA / TODAS LAS TALLAS

F FALDA USE LAS PIEZAS 1 2 3 4 5 6 7 8 9 10

- 4A** 44" 45" (115CM) CON PELUSA / TODAS LAS TALLAS
- 4B** 58" 60" (150CM) CON PELUSA / TALLAS 6 8 10 12 14 16
- 4C** 58" 60" (150CM) CON PELUSA / TALLAS 18 20 22

PARTES SUPERIORES CONTRASTANTES DEL FRENTE Y DE LA PRETINA INFERIOR

USE LAS PIEZAS 1 6 8

- 4D** 44" 45" (115CM) CON PELUSA / TODAS LAS TALLAS
- 4E** 58" 60" (150CM) CON PELUSA / TODAS LAS TALLAS

SELVAGE(S) / SEL.(S)=ORILLO(S)
FOLD=DOBLEZ
CROSSWISE FOLD=DOBLEZ TRANSVERSAL

Sewing Directions

FABRIC KEY	RIGHT SIDE	WRONG SIDE	INTERFACING	LINING

Read **General Directions** on page 1 before you begin.

- Pin or baste seams within the seam allowance since pin holes remain in fabric.
- Basting tape is another ideal method to hold seam allowances together and avoid slipping of fabric.
- For hand-basting or sewing, use a fine, sharp size 10 needle and a thimble.
- For machine-sewing, use medium but balanced tension and 8 to 10 stitches per inch (2.5cm)...size 11/12 or even a 9/10 ball point needle and 100% polyester or polyester core thread.
- For top-stitching, use a size 16 needle and silk, polyester buttonhole twist or top-stitching thread.
- When feeding fabric through machine, hold it “taut” in front of and behind the machine needle as you sew. **DO NOT** stretch.
- Press seams open with fingers or press on **WRONG** side with iron set at a low temperature setting and a press cloth. **DO NOT USE A STEAM IRON.** WE DO NOT RECOMMEND PRESSING ON **RIGHT** SIDE OF **FABRIC**. When pressing synthetic leather or vinyl, we recommend covering your ironing board and garment with brown paper to prevent melting.
- Always test on fashion fabric scraps.
- Some fabrics may be stubborn to feed through your sewing machine. Place strips of tissue paper over seams and edges of garment to be stitched. Tear away paper after stitching. This method will give you even stitches without any puckers.

PATTERN PIECES WILL BE IDENTIFIED BY NUMBERS THE FIRST TIME THEY ARE BEING USED.









SKIRT A, B, C, D, E, F

STAY-STITCHING A, B, C, D, E

1. Stay-stitch upper edge of front (1), side front (2), back (3) and side back (4) 1/2” (1.3cm) from cut edges in direction of arrows.
This stitching stays in permanently and helps prevent stretching on curved edges.
Stay-stitching will not be shown in the following illustrations.

FRONT OVERLAY AND STAY-STITCHING F

2. Pin **WRONG** side of front overlay (1) to **RIGHT** side of front, matching centers and pleat lines, having raw edges even. Machine-baste raw edges together.
3. Stay-stitch upper edge of side front (2), back (3) and side back (4) 1/2” (1.3cm) from cut edges in direction of arrows.
This stitching stays in permanently and helps prevent stretching on curved edges.
Stay-stitching will not be shown in the following illustrations.



SIDE FRONT SEAMS AND PLEATS A, D, E, F

4. With **RIGHT** sides together, stitch front to side front sections at side front seams. Press seams toward center.
5. To make pleats in front, on **OUTSIDE**, fold along broken lines in front.
Bring folds to broken lines in side front; pin.
Baste across upper edge of pleats.


SIDE FRONT SEAMS AND PLEATS B, C

6. To stitch side front seam and make pleat, with **RIGHT** sides together, pin front to side front sections, matching notches, broken lines and small dots. Stitch side front seam from lower edge to upper edge. Stitch along broken lines from small dot to upper edge; back-stitch at small dot to reinforce pleat.


7. Press seams and pleats toward center.
Baste across upper edge of pleat.

8. **FOR VIEW B-** On **OUTSIDE**, using embroidery thread, work running stitches on front and side front 5/8” (1.5cm) from pleat seam, forming points at the small dot and stitching through all thicknesses, as shown.

RUNNING STITCH - Working from right to left, weave the needle in and out of the fabric at regular intervals. Keep the stitches uniform in size.




9. FOR VIEW C- Close zipper. Press under lower end of zipper tape. On OUTSIDE, with zipper face up, center zipper teeth along pleat seam, placing pressed end at small dot. Stitch close to edges and pressed end of tape, using an adjustable zipper foot. Baste along seam line across upper edge of zipper.




SEAMS A, B, C, D, F

10. Stitch back to side back sections at side back seams. Stitch front to back at RIGHT side seam only.



SEAMS E


11. Stitch back to side back sections at side back seams. Stitch front to back at RIGHT side seam only.




WAISTBAND OVERLAY F

12. Pin WRONG side of lower front waistband overlay (6) to RIGHT side of lower front waistband, matching centers. Machine-baste raw edges together. Machine-baste lower back waistband overlay (8) to back waistband in same manner.


CONTINUE AS FOLLOWS FOR ALL VIEWS




13. Apply fusible interfacing to WRONG side of upper front waistband (5) and lower front waistband (6), following manufacturer's directions. With RIGHT sides together, stitch upper front waistband to lower front waistband, matching centers and notches. Trim seam.



14. Apply fusible interfacing to WRONG side of upper back waistband (7) and lower back waistband (8), following manufacturer's directions. With RIGHT sides together, stitch upper back waistband to lower back waistband, matching centers and notches. Trim seam. Stitch front waistband to back waistband at RIGHT side seam.




15. FOR VIEW D- On OUTSIDE, pin trim to lower waistband, placing edge along seam. Stitch close to long edges of trim.



16. FOR ALL VIEWS- With RIGHT sides together, pin waistband to skirt, matching centers, RIGHT side seams, and having opening edges even. Stitch. Trim seam. Press seam toward band.


NOTE: Need help? Visit www.simplicity.com/videoesewinvisiblezip for further instructions.

Stitch the invisible zipper using an invisible zipper foot. Before you begin, be sure to line up your needle with the center of the invisible zipper foot or you may break your needle. When the coils are to the LEFT of the raw edge use the LEFT groove and when the coils are to the RIGHT of the raw edge use the RIGHT groove.




17. Open the zipper and press the tape flat on the WRONG side unrolling the coils. Do not press the coils. (Use a low iron setting.)


On OUTSIDE, pin RIGHT side of the zipper face down on the RIGHT side of the zipper opening. Have the coil along the seam line, the tape within the seam allowance and the top stop 3/4" (2cm) below upper edge, as shown. Hand-baste along center of the tape. Position zipper foot at the top of the zipper with RIGHT groove of the foot over coil. Stitch along tape to the notch. Back-stitch to reinforce.




18. Pin the remaining half of the zipper to the LEFT side of the zipper opening in same manner. Make sure the upper and lower edges of the garment are even and the waistband seams match. Hand-baste along the center of the tape. Position zipper foot at the top of the zipper with LEFT groove over the coil. Stitch along tape to the notch. Back-stitch to reinforce.




19. Close zipper and check that it is invisible from the OUTSIDE. Pull the free ends of the zipper tape away from the seam allowance. Pin remaining LEFT side seam together below zipper. Position zipper foot all the way to the LEFT so the needle goes down through the outer notch of the foot. Start stitching seam 1/4" (6mm) above lowest stitch and slightly to the LEFT. Stitch seam for about 3" (7.5cm). Stitch remainder of seam using your regular presser foot. If you prefer, open out each seam allowance at end of zipper and stitch tape to seam allowance.




20. Apply fusible interfacing to front facing (9) and back facing (10) sections. Stitch front to back at RIGHT side seam. Zig-zag or overlock/serge lower edge of band facing.




21. Open out LEFT side opening edges. With RIGHT sides together, pin facing to waistband at upper edge, matching centers and RIGHT side seams. Stitch. Trim seam; clip curves.



22. Understitch by pressing facing and seam away from skirt, stitching through facing and seam allowances close to seam.




23. To finish LEFT side opening edges, turn facing to OUTSIDE along seam, as shown. Pin LEFT side opening edges together. Using an adjustable zipper foot, stitch across facing 1/2" (1.3cm) from back edges, keeping zipper teeth free. Trim corners.



24. Turn facing and LEFT side edges to INSIDE, rolling zipper teeth back in place; press. On INSIDE, pin finished edge of facing over seam, placing pins on OUTSIDE. (Finished edge of facing extends below seam.) On OUTSIDE, stitch in the ditch or groove of waistband seam, catching in finished edge of facing on INSIDE.


HEM A, B, C, D

25. Mark length.
Press up hem along marking.
Mark depth of hem; trim evenly.
To form narrow hem, tuck under raw edge to meet crease.
Press. Stitch hem in place.



HEM E, F

26. Press up hem. To form narrow hem, tuck under raw edge to meet crease.
Press. Stitch hem in place.



Español

LAS PIEZAS DE PATRÓN SON INDICADAS POR NÚMEROS CUANDO SON USADAS POR LA PRIMERA VEZ.

FALDAS A, B, C, D, E, F

PUNTADA DE SOSTÉN A, B, C, D, E

1. Haga una puntada de sostén en el borde superior del escote (1), de la parte lateral delantera (2), de la parte trasera (3) y de la parte lateral trasera (4), a 1/2" (1.3cm) de los bordes cortados, en la dirección de las flechas.
La puntada de sostén es permanente y sirve para prevenir que se estiren los bordes curvos.
La puntada de sostén no aparecerá en las ilustraciones siguientes.

PARTE SUPERIOR DEL FRENTE Y PUNTADA DE SOSTÉN F

2. Prenda con alfileres el REVÉS de la parte superior delantera (1) en el DERECHO del frente, casando los centros y las líneas de pliegue con los bordes no terminados parejos. Hilvane a máquina los bordes no terminados.
3. Haga una puntada de sostén en el borde superior de la parte lateral delantera (2), de la parte trasera (3) y de la parte lateral trasera (4), a 1/2" (1.3cm) de los bordes cortados, en la dirección de las flechas.
La puntada de sostén es permanente y sirve para prevenir que se estiren los bordes curvos.
La puntada de sostén no aparecerá en las ilustraciones siguientes.

COSTURAS LATERALES DEL FRENTE Y PLIEGUES A, D, E, F

4. DERECHO CON DERECHO, cosa las partes laterales del frente en el frente por las costuras laterales del frente. Planche las costuras hacia el centro.
5. Para hacer los pliegues en el frente, en el EXTERIOR, doble a lo largo de las líneas interrumpidas del el frente. Coloque los dobleces en las líneas interrumpidas de la parte lateral del frente; prenda con alfileres.
Hilvane a través de los bordes superiores de los pliegues.

COSTURAS LATERALES DEL FRENTE Y PLIEGUES B, C

6. Para coser la costura lateral del frente y hacer el pliegue, DERECHO CON DERECHO, prenda con alfileres las partes laterales del frente en el frente, casando las muescas, las líneas interrumpidas y los puntos pequeños. Cosa la costura lateral del frente desde el borde inferior hasta el borde superior. Cosa a lo largo de las líneas interrumpidas desde el punto pequeño hasta el borde superior; retroceda el pespunte en el punto pequeño para reforzar el pliegue.
7. Planche las costuras y los pliegues hacia el centro. Hilvane a través del borde superior del pliegue.
8. PARA EL MODELO B- En el EXTERIOR, usando hilo de bordar, cosa con puntadas rectas en el frente y la parte lateral del frente, a 5/8" (1.5cm) de la costura del pliegue, formando puntas en el punto pequeño y atrapando todos los espesores, como se muestra.
PUNTADAS RECTAS - Trabajando de la derecha a la izquierda, inserte la aguja en la tela y sáquela con intervalos regulares. Haga puntadas del mismo tamaño.
9. PARA EL MODELO C- Cierre la cremallera. Planche hacia dentro el extremo del galón de la cremallera. En el EXTERIOR, con el derecho de la cremallera hacia Ud., coloque los dientes a lo largo de la costura del pliegue, colocando el extremo planchado en el punto pequeño. Cosa cerca de los bordes y del extremo planchado del galón con un prensatelas para cremalleras. Hilvane a lo largo de la línea de costura a través del borde superior de la cremallera.

COSTURAS A, B, C, D, F

10. Cosa las partes laterales traseras en la parte trasera por las costuras laterales traseras. Cosa el frente en la parte trasera por la costura del lado DERECHO solamente.

COSTURAS E

11. Cosa las partes laterales traseras en la parte trasera por las costuras laterales traseras. Cosa el frente en la parte trasera por la costura del lado DERECHO solamente

PARTE SUPERIOR DE LA PRETINA F

12. Prenda con alfileres el REVÉS de la parte superior de la pretina inferior delantera (6) en el DERECHO de la pretina inferior delantera, casando los centros. Hilvane juntos los bordes no terminados a maquina.
Hilvane a maquina la parte superior de la pretina inferior trasera (8) en la pretina trasera de la misma manera.

CONTINUE COMO SIGUE PARA TODOS LOS MODELOS

13. Coloque la entretela adhesiva en el REVÉS de la pretina superior delantera (5) y de la pretina inferior delantera (6), siguiendo el modo de uso. DERECHO CON DERECHO, cosa la pretina superior delantera en el la pretina inferior delantera casando los centros y las muescas. Recorte la costura.

14. Coloque la entretela adhesiva en el REVÉS de la pretina superior trasera (7) y de la pretina inferior trasera (8), siguiendo el modo de uso. DERECHO CON DERECHO, cosa la pretina superior trasera en el la pretina inferior trasera casando los centros y las muescas. Recorte la costura.
Cosa la pretina delantera en la pretina trasera por la costura de la do DERECHO

15. PARA EL MODELO D- En el EXTERIOR, prenda con alfileres el adorno en la pretina inferior, colocando el borde a lo largo de la costura. Cosa cerca de los bordes largos del adorno.

16. PARA TODOS LOS MODELOS- DERECHO CON DERECHO, prenda con alfileres la pretina en la falda, casando los centros, las costuras del lado DERECHO y juntando los bordes de la abertura. Cosa. Recorte la costura. Planche la costura hacia la pretina.

NOTA: Necesita ayuda? Visite nuestra página www.simplicity.com/ indivisiblemente para más información.

Cosa la cremallera con un prensatelas para cremallera invisible. Antes de comenzar, no olvide de colocar la aguja en el centro del prensatelas para evitar que se rompa. Si los dientes están a la IZQUIERDA del borde no terminado, use el surco IZQUIERDO y si están a la DERECHO, use el surco DERECHO.

17. Abra la cremallera y planche el galón sin atrapar los dientes (con la plancha sobre temperatura baja).
En el EXTERIOR, prenda con alfileres el lado DERECHO del revés de la cremallera en el borde delantero DERECHO de la abertura, con los dientes a lo largo de la línea de la costura, el galón en el margen de la costura y el tope superior a 3/4" (2cm) debajo del borde superior como se muestra.
Hilvane en el centro del galón de la cremallera. Coloque el prensatelas en el extremo superior de la cremallera con el surco DERECHO sobre los dientes. Cosa a lo largo del galón hasta la muesca. Retroceda el pespunte para reforzar la costura.

18. Prenda con alfileres la otra mitad de la cremallera en el borde IZQUIERDO de la abertura de la misma manera. Asegúrese de bien alinear los bordes superior e inferior de la prenda. Hilvane a mano en el centro del galón. Coloque el prensatelas en el extremo superior de la cremallera con el surco IZQUIERDO sobre los dientes. Cosa a lo largo del galón hasta la jaladera. Retroceda el pespunte para reforzar la costura.

19. Cierre la cremallera e averigüe que sea invisible en el EXTERIOR. Vuelva los extremos del galón fuera del margen de la costura. Prenda con alfileres la costura del lado IZQUIERDO debajo de la cremallera. Coloque el prensatelas a la IZQUIERDA para coser en la muesca exterior. Empiece a coser la costura a 1/4" (6mm) arriba de la última puntada y ligeramente a la IZQUIERDA. Cosa la costura por aproximadamente 3" (7.5cm). Cosa el resto de la costura con un prensatelas corriente. Si Ud. lo prefiera, abra el margen de la costura en el extremo de la cremallera y cosa el galón en el margen de la costura.

20. Coloque la entretela adhesiva en la vista delantera (9) y la vista trasera (10). Cosa el frente en la parte trasera por la costura del lado DERECHO. Cosa con puntadas de zig-zag o de overlock/sobrehilado en el borde inferior del forro de la banda.

21. Abra los bordes de la abertura del lado IZQUIERDO. DERECHO CON DERECHO, prenda con alfileres el forro den la pretina a lo largo del borde superior, casando los centros y las costuras del lado DERECHO. Cosa. Recorte la costura; haga cortes en las curvas.

22. Para hacer la costura oculta, planche el forro y la costura fuera de la falda y cosa a través de los márgenes de costura, cerca de la costura.

23. Para acabar los bordes de la abertura del lado IZQUIERDO, vuelva la vista hacia el EXTERIOR, a lo largo de la costura, como se muestra. Prenda juntos con alfileres los bordes de la abertura de lado IZQUIERDO. Usando un prensatelas ajustable para cremalleras, cosa a través de la vista, a 1/2" (1.3cm) de los bordes traseros, sin atrapar los dientes de la cremallera. Sesgue las esquinas.
24. Vuelva la vista y los bordes del lado IZQUIERDO hacia el INTERIOR, volviendo los dientes de la cremallera en su sitio; planche.
En el INTERIOR, prenda con alfileres el borde terminado de la vista en la costura, colocando los alfileres en el EXTERIOR. (El borde terminado de la vista sobre-pasa debajo de la costura). En el EXTERIOR, cosa en el surco de la costura de la pretina atrapando el borde terminado de la vista en el INTERIOR.

DOBLADILLO A, B, C, D

25. Marque el largo. Planche el dobladillo a lo largo de la marca.
Marque el ancho del dobladillo; recorte uniformemente.
Para formar el dobladillo angosto, vuelva el borde no terminado hacia dentro colocándolo en el doblez.
Planche. Cosa el dobladillo.

DOBLADILLO E, F

26. Planche el dobladillo. Para formar el dobladillo angosto, vuelva hacia dentro el borde no terminado colocándolo en el doblez. Planche. Cosa el dobladillo.