


N Newsboy Cap



*Refer another pdf file for the pattern.

* Inch notations are approximate.

MATERIALS

- Main Fabric /140 cm (55") width
Length : 0.5 m (0.54 yds)
- Lining Fabric / 140 cm (55") width
Length : 0.5 m (0.54 yds)
- Interfacing : Thick and heavy type enough for the brim.
- Tape or ribbon for inner band like grosgrain or twill tape
width : 3 ~ 4 cm (1 1/4" ~1 5/8")
length : 60-65cm (0.66-0.7 yds)


PATTERN PREPARATION

- Print out the pattern pages. The data size is 100%. Print without scaling.
Check the test square (10 X 10 cm (≈ 4")) on the pattern page to insure that your pattern has printed correctly.
 - Cut off the margins around each page.
 - Assemble the pattern along the numbers as shown in the diagram. Tape the pieces together.
(With copy shop size print, you don't need these steps.)
 - Adjust the pattern if necessary to fit your measurements.
 - Cut out your pattern.
- * This pattern includes seam allowances, also shows seamlines and hemlines. You may choose your pattern outline.


LAYOUT / CUTOUT / MARKING / INTERFACING

width : 140cm // 55"

Seam allowance : 1.2cm (≈ 1/2")



Lining fabric




- Preshrink your fabrics, if needed.
 - Place the pattern pieces on your fabric referring to the diagrams. Make sure to follow the grainline on the pattern.
 - Cut your fabrics.
* If your fabrics have some print or pattern, such as the plaid, make sure to match it on the different pieces.
 - Mark all pattern markings onto the wrong side of your fabric (notches, center etc.).
 - Press the interfacing, according to the diagrams, onto the wrong side of the fabric.
 - Choose the interfacing suitable for your fabrics.
Check it by testing if you are not sure.
- * it is recommended making a muslin for the perfect fit before cutting your fashion fabric.

LEGEND

 Right side shell fabric


 Right side lining

 Wrong side fabric/lining


 Interfacing

CAP

- 1 Fold the Upper Cap piece in half right sides together. Sew the back dart.




- 2 Press the seam open.



- 3 Place the Side Cap and the Upper cap pieces right sides together. Sew the side seam.

*Use the pattern notches as a guide




- 4 Press the seam open.

- 5 Finish the lining pieces in the same way.


BRIM

- 1 Place the Brim pieces right sides together. Sew the seam as shown.




- 2 Clip into the curve.

*Be careful not to cut into the stitching.




- 4 Turn it to the right side. Press and topstitch.




ASSEMBLE

- 1 Set the Lining piece into the Cap(shell), wrong sides together, Baste the edge.




- 2 Place the Brim onto the Cap, using the pattern notches as a guide. Stitch the edge as shown.




- 3 Fold and press the edge.


- 4 Place the Tape inside the cap along the edge.



- 5 Stitch the lower edge.



- 6 Stitch the front of the Side Cap to the Brim to fix it.



FINISHED !