

We love
STYLE

Turn up the style **TROUSERS**

Sew these comfortable but chic trousers for an all-season staple

Project **FREYA GILBERT & SARAH WADEY**
from **Crafty Sew & So** www.craftysewandso.com



MY HANDMADE
WARDROBE

Freya and Sarah co-own Crafty Sew & So, a Leicester-based fabric shop and sewing studio. They launched their pattern range, My Handmade Wardrobe Patterns, in 2017 and design modern sewing patterns that everyone can sew. Visit www.craftysewandso.com for more!





MATERIALS & TOOLS:

- 3m of 110cm/45" wide fabric or 2.5m of 150cm/60" wide fabric
- Your waist measurement in 20mm wide elastic
- templates downloaded from www.craftworld.com/cms/love-sewing

NOTES:

All seam allowances are 1.5cm unless stated otherwise. We recommend using an overlocker or zigzag stitch on a sewing machine to finish the edges before constructing using a straight stitch on the sewing machine.

HOW TO MAKE

1. Place the upper pocket bag over the front aligning raw edges and dots at the pocket opening. Pin and sew from the top of the pocket bag to the bottom at the side seam. (See Pic A.)
2. Snip into the seam allowance to the dot. (See Pic B.)
3. Flip the pocket bag to the inside of the trouser and press the pocket bag opening edge. (See Pic C.)
4. Topstitch the pocket opening 5mm from the

folded pocket opening edge. (See Pic D.)

5. Align the top of the upper pocket bag where marked on the pattern and baste in place, stitching only to dot. (See Pic E.)

6. Place the lower pocket bag over the upper pocket bag RST. Pin and sew around the curved edge to join the two pocket bags. Finish curved pocket bag edges together. (See pics F & G.)

7. Align the pocket bag with the side seam of the front leg and the waistline, matching all notches and baste in place. (See Pic H.)

8. Join two front panels at the crotch seam and press the seam open. (See pics I & J)



9. Join two back panels at the crotch seam and press the seam open. (See Pic K.)

10. Join the front and back at the inside leg, press the seams open. (See pics L & M.)

11. Join the front and back at the side seams, press the seams open. (See Pic N.)












12. Finish the whole top edge of the trouser. Press the waistline down where

LAYPLAN:



SIZE CHART: IN CM

Size	1	2	3	4	5	6	7	8
Bust	82	87	92	97	102	107	114	126
Waist	66	71	76	81	87	93	99	109
Hip	90	95	100	105	110	115	120	130



marked. Pin and baste waistband in place. To create the elastic channel, top stitch two rows of stitching where marked, leaving a gap in the lower row only at the back of the garment to insert elastic. (See Pic O.)

13. Insert elastic, try on trousers, and adjust the elastic to fit. Overlap and join elastic ends. Topstitch to finish and close the gap in the elastic channel. (See pics P-R.)

14. Finish the edge of the hem. Turn the hem up to where marked and topstitch. (See pics S & T.)


15. Fold and press the turn-up to the outside of the trousers and hand stitch in place at both side seams.

16. To make the belt, fold the fabric in half lengthwise RST and sew along one short edge, then halfway along the long edge. Leave a gap for turning, then continue to sew along the rest of the long edge and the other short edge. Trim seam allowance to 5mm. (See Pic U.) Turn the belt the right way out and press. Close the gap with hand stitching.

17. To make the belt loops, fold the fabric in half lengthwise RST and stitch. Trim seam allowance to 5mm. Turn the loop the right way out. Cut belt loops into five pieces measuring 8cm each. Fold the raw edges in 1cm at each end and top stitch to finish. (See pics V & W.)



TROUSERS



MHW045 TAPERED TROUSERS

3CM
TEST
SQUARE

PATTERN SIZE KEY

SIZE ① ······

SIZE ② ······

SIZE ③ ·—·—


SIZE ④ ———

SIZE ⑤ - - - - -

SIZE ⑥ ······

SIZE ⑦ - - - - -

SIZE ⑧ ———




2



STITCHING LINE

STITCHING LINE


3




4




5



6



7





9



BASTING LINE




MY HANDMADE
WARDROBE

TAPERED TROUSERS
UPPER POCKET BAG
CUT 2

1.5CM SEAM ALLOWANCE

10



MADE
OBE

ERS
AG

OWANCE



12




MY HANDMADE
WARDROBE


TAPERED TROUSERS
BACK
CUT 2


1.5CM SEAM ALLOWANCE

B












MY HANDMADE
WARDROBE


TAPERED TROUSERS
FRONT
CUT 2

1.5CM SEAM ALLOWANCE

A







19

C



20



















29



MY HANDMADE
WARDROBE

TAPERED TROUSERS
LOWER POCKET BAG
CUT 2

1.5CM SEAM ALLOWANCE

D




30


E

NCE



















38



MY HANDMADE
WARDROBE

TAPERED TROUSERS
BELT LOOPS
CUT 1


1.5CM SEAM ALLOWANCE

F



40





42

WAKE
TAPERED TRO
TIE BELT
CUT 1

1.5CM SEAM A



E

MODEL

43


USERS

ALLOWANCE



44






46







49







