


MYIMAGE

PDF PATTERN **S1056**
Dress "Roxy"



Sizes:

EU 34-52

US 4-22

UK 6-24

Difficulty:

4/5

Instructions:

English

Paper size:

**A4 and
US Letter**



—digital—
PDF
 —pattern—



General instructions

Thank you very much!

Thank you very much for choosing this pattern! Have you ever made PDF patterns before? No problem if you haven't; in about 2 minutes you will know exactly how it works!

Environment friendly!

There are several ways to offer PDF patterns and every designer has different ideas about it. To minimize wasting expensive ink, we have chosen to place the pattern pieces in a way that you need a minimum of A4/US letter pages.

You can choose between tracing the pattern pieces from the 9-page pattern sheet or print a couple more pages so you can start cutting immediately. We give you a choice, you decide!

Materials

Our PDF pattern sheet is very straightforward and easy to put together. For this you'll need the following:

- A4/US letter printer
- A4/US letter pages
- Paper scissors
- Roll tape
- Pencil/pen
- Pattern (tracing) paper

Choose your way

There are two ways to cut out the pieces:

A. You can create a pattern sheet, like the ones included with sewing magazines. Then trace the pieces and and cut them out.

- You only need 16 A4/US letter pages
- You can re-use the pattern sheet

B. You can print all pieces separately, so you can start cutting them immediately.

- It take less time in total

Both ways are described on the following page. Choose a way and follow the rest of the steps.

-- 5 cm. -->

IMPORTANT:

When printed this square must be exactly 5 x 5 cm. If it isn't, the PDF isn't printed at 100% size. Need help? Please email us!

<-- 5 cm. -->

From PDF to pattern pieces

1. Print this PDF file

IMPORTANT: Make sure you print the PDF at 100% size. Disable the option "Fit to Page".

After printing you can check the size by measuring the square on this page.

Tip: Want to save ink? Print the file without color.

2. Trim the edges of the paper

Trim the edges off the pages at the sides marked with dotted lines, see ✂

IMPORTANT: Trim OVER the dotted lines, to trim away the lines. Do this carefully and don't trim away parts of the pattern lines.

3. Lay the pages together and tape them

Place the sides with the same letters together; A to A, B to B, etc. Pick up a page, place it above or below the previous one and tape it together.

IMPORTANT: Place the pattern lines of all pages carefully against each other. All lines should fit smoothly.

Seam allowances

IMPORTANT: All pattern pieces are made without seam allowance. We advise to cut 1 to 1,5 cm. / 0.4 to 0.6" extra for seam allowance and 3 to 4 cm. / 1.2 to 1.6" for the seams.

Need help? No problem!

We have tried to make this pattern as simple as possible with the goal to give you more time for the fun part, the making of the garment itself!

But there is always room for improvement! If you have comments or questions about our patterns, please send an email to info@madebyoranges.com. We will try to help you as soon as possible!

More patterns & magazines!

Our PDF patterns, sewing pattern magazines and subscriptions can be found in our international webshop:

www.madebyoranges.com



My Image 18




B-Trendy 12



My Image Special 2

Pattern pieces layout



Choose your way

A. Create a pattern sheet

You need all 16 pages once. Lay and tape the pages together, trace the pattern pieces and cut them out.

B. Create separate pattern pieces

To be able to cut out the pattern pieces immediately, you can print all pieces separately. For this way you need some pages printed out several times, see below.

Piece 1: p. 19

Piece 2: p. 13, 14, 17, 18

Piece 3: p. 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16

Piece 4: p. 16

Piece 5: p. 6, 7, 10, 11, 14, 15


Piece 6: p. 5, 6, 9, 10

Piece 7: p. 7, 8, 11, 12, 15, 16, 19, 20

Print for each pattern piece the mentioned pages, lay the pages of each piece together and tape them. Now you can cut them out immediately.

Instructions

EU sizes: 34-36-38-40-42-44-46-48-50-52
Difficulty: 4/5



Fabric usage:
130-135-140-140-145-150-150-150-155-160 cm.

Lining fabric usage:
95-95-95-95-95-100-100-100-100-100 cm.

Suggested fabrics:
- Cotton-polyester
- Viscose-polyester

Suggested lining fabric:
- *Stretchable fabric!*

Back length: +/- 97 cm.

Materials:
- Thread
- Decorative ribbon 210-260 cm.
- Button 1x



Pattern pieces:
1. Upper front 1x
2. Front 1x
3. Lower front 1x
4. Side front 1x
5. Back 1x
6. Sleeve 2x
7. Front lining 1x

Enlarge the back piece with 35 cm.

Back piece lining: Cut the back piece +/- 14 cm. shorter. Check the side seams of front and back.


Instructions:
1. Stitch the darts in the front piece. 2. Stitch the upper front piece to the front piece. 3. Stitch the side front piece to the lower front piece. 4. Stitch the lower front piece to the front piece. 5. Stitch the side seams. **Lining:** 6. Stitch the darts in the front piece. 7. Stitch the side seams. 8. Slide the lining dress into the dress. 9. Stitch the front piece (lining) onto the seam of the front piece and upper front piece. 10. Pin the shoulder seam of the lining dress onto the shoulder seam of the back piece. 11. Stitch the shoulder seams of the front and back piece. 12. Stitch the sleeve. 13. Stitch the sleeve into the armhole. Stitch the armholes of the lining at the same time. Following the marks on the pattern. 14. Hem the bottom of the sleeve. 15. Stitch the decorative ribbon along the back piece split. 16. Stitch the decorative ribbon along the neck. Stitch a loop at the lefthand side of the split. 17. Sew the button at the other side of the split. 18. Stitch the decorative ribbon at the bottom of the dress.

Fabric layout



Size chart

A. Chest width
B. Waist width
C. Hip width
D. Back length



Choose the pattern size that compares best to your measured size.

Body length: 170 cm. / 5'7"

	34 US 4 UK 6	36 US 6 UK 8	38 US 8 UK 10	40 US 10 UK 12	42 US 12 UK 14	44 US 14 UK 16	46 US 16 UK 18	48 US 18 UK 20	50 US 20 UK 22	52 US 22 UK 24
A	83 cm. 32.7"	87 cm. 34.3"	91 cm. 35.8"	95 cm. 37.4"	99 cm. 39"	103 cm. 40.6"	108 cm. 42.5"	113 cm. 44.5"	118 cm. 46.5"	124 cm. 48.8"
B	66 cm. 26.0"	69 cm. 27.2"	72 cm. 28.3"	76 cm. 29.9"	80 cm. 31.5"	84 cm. 33.1"	89 cm. 35.0"	94.5 cm. 37.2"	101 cm. 39.8"	107.5 cm. 42.3"
C	92 cm. 36.2"	95 cm. 37.4"	98 cm. 38.6"	101 cm. 39.8"	105 cm. 41.3"	109 cm. 42.9"	113 cm. 44.5"	117 cm. 46.1"	122 cm. 48.0"	127 cm. 50.0"
D	41.5 cm. 16.3"	41.7 cm. 16.4"	41.9 cm. 16.5"	42.1 cm. 16.6"	42.3 cm. 16.7"	42.5 cm. 16.7"	42.7 cm. 16.8"	42.9 cm. 16.9"	43.1 cm. 17.0"	43.3 cm. 17.0"

MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52

34
36
38
40
42
44
46
48
50
52


3

6

A


D

5



MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52

SIZES 34-52



7




MY IMAGE PDF PATTERN

DRESS "ROXY"


SIZES 34-52

C

G



MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52



H

L


I

E

RVD/FL/STRAIGHT GRAIN/FIL DROIT


MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52

MV RVD/VM FL/CF STRAIGHT GRAIN/MA DROIT FIL



MA STOFV/HM STOFFBR/CB FABRIC FOLD/MD PLI DU TISSU

MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52



MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52

MV STOFV/M STOFFBR/CF FABRIC FOLD/MA P/LI DU TISSU


K

O

MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52

R

MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52



MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52

VERLENGEN/VERLANGERN/ENLARGE/ALARGIR 35 CM.

VERLENGEN/VERLANGERN/ENLARGE/ALARGIR 35 CM.

VERLENGEN/VERLANGERN/ENLARGE/ALARGIR 35 CM.

N

RVD/FL/STRAIGHT GRAIN/FIL DROIT

MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52


4

16

U




Q



R

MV STOFV/M STOFFBR/CE FABRIC FOLD/MA PLI DU TISSU



MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52

2



S

MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52

W

V

34

36

38

40

42

44

46

48

50

52



T

34

36

38

40

42

44

46

48

50

52

X

MV STOFFV/M STOFFBR
/CF FABRIC FOLD/
MA PLI DU TISSU

MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52

1

34

36

38

40

42

44

46

48

50

52



U

L

X

MY IMAGE PDF PATTERN
DRESS "ROXY"
SIZES 34-52